




PHLEARN

PRO

LUTs for Photo & Video

Install Guide

For Photoshop, Premiere Pro, DaVinci Resolve and Final Cut Pro

THANK YOU

Thanks for being a PRO member.

This pack is part of your membership. The LUTs work on photos and on video. Here is how to load them.

1

Unzip

Double-click the zip on a Mac. On Windows, right-click and choose Extract All.

2

Find your app

Photoshop: pages 4 and 5. Premiere Pro: page 6. DaVinci Resolve: page 7. Final Cut Pro: page 8.

3

Load a .CUBE file

Use the .CUBE version unless your software asks for something else.

WHAT'S IN YOUR PACK

5 LUTs, four formats

Every PHLEARN LUT pack is built the same way, so these steps work for all 35.

A LUT is a color grade saved as a file. Load it in Photoshop or your video editor to apply the look.

.CUBE**Use this one**

Works in Photoshop and almost every video editor

**.3DL .CSP
.ICC****For other software**

Only if your app does not accept .CUBE

PHOTOSHOP • QUICK INSTALL

Load a LUT into one document

The fastest way to try a LUT. Nothing gets installed.

- 1 Open a photo in Photoshop.
- 2 Choose **Layer > New Adjustment Layer > Color Lookup** and click OK.
- 3 In the Properties panel, open the **3DLUT File** menu and choose **Load 3D LUT**.
- 4 Select a **.CUBE** file from the **Photoshop Quick Install** folder and click Load.
- 5 Set the strength with the layer's **Opacity**. Most LUTs sit best between 40 and 80 percent.

WHERE TO CLICK

Layer

Menu bar at the top

**New Adjustment Layer > Color Lookup**

Click OK

**3DLUT File**

Menu in the Properties panel

**Load 3D LUT**

Pick a .CUBE file, then click Load

PHOTOSHOP • PERMANENT INSTALL

Add the pack to the LUT menu

- 1** Open the **Photoshop Quick Install** folder, select all the **.CUBE** files and copy them.
- 2** Open Photoshop's **3DLUTs** folder (paths below).
- 3** Paste the files in. Your computer may ask for your password.
- 4** Restart Photoshop.
- 5** Add a Color Lookup adjustment layer and pick the LUT from the **3DLUT File** menu.

Mac: Applications > Adobe Photoshop 2026 > Presets > 3DLUTs

Windows: C: > Program Files > Adobe > Adobe Photoshop 2026 >

Presets > 3DLUTs

Use your version year if it is not 2026.

WHERE TO CLICK

Photoshop Quick Install

Copy all the .CUBE files

**Presets > 3DLUTs**

Inside the Adobe Photoshop folder. Paste here

**Restart Photoshop**

Quit and reopen

**3DLUT File**

The PHLEARN LUTs are now in the list

VIDEO

Premiere Pro

- 1** Select a clip and open **Lumetri Color** (Window > Lumetri Color).
- 2** Click the **Creative** heading to expand it.
- 3** Open the **Look** menu and choose **Browse**, near the top of the list.
- 4** Select a **.CUBE** file from the Photoshop Quick Install folder and click Open.
- 5** Set the **Intensity** slider. Most footage looks best between 50 and 80.

Keep them in the **Look** menu. Copy the .CUBE files into Adobe > Common > LUTs > Creative and restart Premiere Pro. Full folder paths: phlearn.com/install-luts

WHERE TO CLICK

Window > Lumetri Color

With a clip selected

**Creative**

Click the heading to expand it

**Look**

Menu at the top of Creative

**Browse**

Pick a .CUBE file, then click Open

VIDEO

DaVinci Resolve

- 1** Click the gear icon at the bottom right to open **Project Settings**, then click **Color Management**.
- 2** Scroll to **Lookup Tables** and click **Open LUT Folder**.
- 3** Create a subfolder named after the pack and copy the **.CUBE** files into it.
- 4** Back in Resolve, click **Update Lists**, then **Save**.
- 5** On the Color page, open the **LUTs** panel at the top left and drag a LUT onto a node.

LUTs missing? Skipping Update Lists is the usual reason. To lower the strength, open the Key panel for that node and reduce Key Output Gain.

WHERE TO CLICK

Project Settings

Gear icon, bottom right

**Color Management**

In the list on the left

**Lookup Tables**

Scroll down to find it

**Open LUT Folder**Copy the **.CUBE** files in, then click Update Lists

VIDEO

Final Cut Pro

- 1** Select a clip and open the **Effects** browser (Cmd+5).
- 2** Choose the **Color** category and double-click **Custom LUT**.
- 3** In the Video inspector, open the **LUT** menu and select **Choose Custom LUT**.
- 4** Select a **.CUBE** file from the Photoshop Quick Install folder and click Open. Leave Input and Output on Rec. 709.
- 5** Set the **Mix** slider to taste.

Next time the LUT is already in the LUT menu. No browsing needed.

WHERE TO CLICK

Effects browser

Cmd+5

**Color**

Category in the list

**Custom LUT**

Double-click to add it to your clip

**LUT > Choose Custom LUT**

In the Video inspector

2 TIPS

Using LUTs well

1

Fix the basics first

Set exposure and white balance, then add the LUT on top. A LUT grades color. It does not correct it.

2

Turn it down

Too strong? Lower the layer opacity in Photoshop, or the Intensity or Mix slider in your video editor.

Using Lightroom Classic, After Effects, Capture One or another app? Steps for those are at phlearn.com/install-luts.

PHLEARN

Thanks for being a PHLEARN PRO member.

Step-by-step install help: phlearn.com/install-luts

Follow PHLEARN on Instagram: [@phlearn](https://www.instagram.com/phlearn)